



MONTREAUX DRILL APRON



What you'll need

- 60cm Montreaux printed drill - olive labels (apron)
- 40cm Montreaux printed drill - red check (sash & pockets)
- Gütermann sewing threads to match fabrics
- Scissors, pins
- Tape measure or ruler
- Iron
- Sewing machine



MONTREAU DRILL APRON

Instructions

1. From olive labels cut a 55cm x 112cm rectangle. From red check cut two 12cm x 112cm strips and two 15cm squares. Trim off selvages.
2. Press under 1cm on each of the 55cm sides and then press under a further 1.5cm. Topstitch side hems in place. Repeat for bottom edge.
3. Press under side and bottom edges of pocket 1.5cm. Press top edge under 1cm then a further 1.5cm and topstitch.
4. Fold apron in half to find centre. Position pockets on apron 10cm from centre and 18cm from top edge, pin in place. Topstitch pockets to apron down sides and across bottom. Backstitch at top of sides.
5. Sew 2 rows of a gathering stitch (long stitch) along top edge, 0.5cm and 1cm from the raw edge. Gently pull stitching to gather top of apron front to a measurement of 60cm. Ensure gathering is even.
6. To make strap, cut one of the fabric strips in half and using a 1cm seam allowance sew one half to each of the shorter ends of the longer strip to create one long strip. Press seams open. Fold in half lengthways, right sides together. Sew together with a 1cm seam allowance, leaving a 60cm opening in the centre. Clip corners, turn right side out and press flat.
7. Insert gathered top of apron front into opening by 1.5cm and pin closed. Topstitch around waistband and strap, enclosing apron front within stitching.



AUSTRALIA
NEW ZEALAND
SINGAPORE

spotlight.com.au or call 1300 305 405
spotlight.co.nz or call 0800 276 222
spotlight.com.sg or call 6733 9808